

See Also

This class has no related objects.

Enumerations

| Name | Values |
|------|--------|
|------|--------|

This class exposes no enumerations.

Constants

| Name | Type | Value |
|---------------------|--------|-------|
| ScrollAlwaysVisible | Number | 1 |
| ScrollAutoHide | Number | 0 |
| ScrollHidden | Number | 2 |

Events

| Definition | Description |
|-----------------------|---|
| PositioningComplete() | Raised when the Wall has finished moving containers either following the Open(ing) or when resized. |

Methods

| Definition | Description |
|---|---|
| AddItem(newPanel as ContainerControl, embed as Boolean = True) | Adds a new Container to the wall. |
| InsertItem(atIndex as Integer, newPanel as ContainerControl, embed as Boolean = True) | Inserts a Container at the specified position. |
| Item(atIndex as Integer) as ContainerControl | Returns the ContainerControl as the specified index. |
| ItemCount() as Integer | Returns the total number of Containers added to the Wall. |
| RemoveAll() | Removes all Containers from the Wall. Does not destroy instances. |
| RemoveItem(atIndex as Integer) | Removes the specified item from the Wall. Does not destroy instances. |

Properties

| Name | Type | Default Value | Description |
|--------------|---------|---------------|---|
| Animated | Boolean | True | When True, item positioning will be animated linearly. |
| ColumnCount | Integer | -1 | A value of -1 will cause the wall to full the display with the maximum number of columns. Anything above 0 will use that many static columns. Column width is equal to the smallest width Container in the display. |
| GutterHeight | Integer | 10 | Vertical distance between Containers. |

| Name | Type | Default Value | Description |
|-------------|---------|---------------|---|
| GutterWidth | Integer | 10 | Horizontal distance between Containers. |
| MinColumns | Integer | 2 | The minimum number of columns that the Wall will use. Helpful for when users resize the Wall too small. This value should never be below 1. |

Examples

This class currently has no examples.

Notes

This class currently has no notes.

From: <https://graffitisuite.com/wiki/> - **GraffitiSuite Documentation**

Permanent link: <https://graffitisuite.com/wiki/doku.php?id=desktop:wall>

Last update: **2019/10/23 05:53**

