

See Also

[GraffitiWebWallPanel](#)

Enumerations

Name	Values
	This class exposes no enumerations.

Constants

Name	Type	Value
		This class exposes no constants.

Events

Definition	Description
KeyPress(KeyCode as Integer, AltKey as Boolean, CtrlKey as Boolean, ShiftKey as Boolean)	Fires when a key or key combination is pressed on the keyboard while the Wall has focus.
ScrollBottom()	Fires when the user has scrolled all the way to the bottom of the available height. Typically used to lazy load more panels.

Methods

Definition	Description
AddPanel(thePanel as GraffitiWebWallPanel)	Adds a panel to the wall.
GetIndex(thePanel as GraffitiWebWallPanel) as Integer	Returns the index of the panel.
GetPanel(panelIndex as Integer) as GraffitiWebWallPanel	Returns the panel at the panelIndex position of the panels array.
InsertPanel(AtIndex as Integer , thePanel as GraffitiWebWallPanel)	Inserts a panel at the given index.
PanelCount() as Integer	The number of panels currently displayed.
RemoveAll()	Remove all panels.
RemovePanel(panelIndex as Integer)	Removes the panel at panelIndex in the panels array from the display.
RemovePanel(thePanel as GraffitiWebWallPanel)	Removes the specified panel.

Properties

Name	Type	Default Value	Description
GutterHeight	Integer	10	The height of the bottom margins of each panel.
GutterWidth	Integer	10	The width of the left/right gutter between the items.
LockUpdate	Boolean	False	Block the display from updating, when true. Update display when set to false.
Panels()	GraffitiWebWallPanel	Nil	The current array of panels. Editing this manually will not cause updates to the display. Please use the built-in methods.

Examples

There are currently no examples for this class.

Changes to this Page

Date	Edit	Editor
08/01/2017	Release 24	Anthony G. Cyphers

From:

<https://graffitisuite.com/wiki/> - **GraffitiSuite Documentation**

Permanent link:

<https://graffitisuite.com/wiki/doku.php?id=web:wall>

Last update: **2019/06/27 04:15**

