

See Also

[GraffitiWebGrid](#)

Enumerations

Name	Values
	This class exposes no enumerations.

Constants

Name	Type	Value
		This class exposes no constants.

Events

Definition	Description
	This class does not expose any events.

Methods

Definition	Description
Constructor(colID as String , colName as String)	Creates an instance of this class with the parameters as property values.

Properties

Name	Type	Default Value	Description
DecimalPlaces	Integer	4	Applies only to columns with FormatType Double.
Editor	GraffitiWebGrid.EditTypes	None	Determines the editor type to be used. See EditTypes Enumeration of GraffitiWebGrid .
Focusable	Boolean	True	Determines whether this column's cells will accept focus.
Formatter	GraffitiWebGrid.FormatTypes	Text	Determines how the values for this column are formatted for display.
HeaderStyle	WebStyle	Nil	Overrides the default style and the StyleHeader property of the containing Grid.
ID	String	""	The identifier for the column's values. Values should be alphanumeric with no special characters such as underscore(_) or hyphen(-), and are case-sensitive. This should not be changed outside the Constructor.
MaxWidth	Integer	0	The maximum width this column can have within the display.
MinWidth	Integer	0	The minimum width this column can have within the display.
Resizable	Boolean	False	Determines whether this column can be resized.

Name	Type	Default Value	Description
Selectable	Boolean	False	Determines whether this column can be selected by clicking the header.
Sortable	Boolean	True	Determines whether the user can sort the rows by clicking this column's header.
Style	WebStyle	Nil	Style applied to row cells in this column. Overrides everything except for style specified by AddCellStyle.
Tag	Variant	Nil	Use for storing things like your database field key. This value has no functional application beyond being used for your reference.
Title	String	""	The displayed title for the column in the header.
Tooltip	String	""	The tip text displayed when the mouse hovers over the column header.
Visible	Boolean	True	The current visible state of the column. This should not be modified outside of the ShowColumn and HideColumn methods of the grid.
Width	Integer	0	The starting width for the column.

Examples

There are currently no examples for this class.

From:

<https://graffitisuite.com/wiki/> - **GraffitiSuite Documentation**

Permanent link:

<https://graffitisuite.com/wiki/doku.php?id=web:grid2column>

Last update: **2019/06/21 09:10**

